CS162
Operating Systems and Systems Programming Lecture 7

Synchronization (Continued)

February 11th, 2015
Prof. John Kubiatowicz
http://cs162.eecs.Berkeley.edu

Recall: How does Thread get started?



- Eventually, `run_new_thread()` will select this TCB and return into beginning of `ThreadRoot()`
  - This really starts the new thread

Goals for Today

- Synchronization Operations
- Higher-level Synchronization Abstractions
  - Semaphores, monitors, and condition variables
- Programming paradigms for concurrent programs

Note: Some slides and/or pictures in the following are adapted from slides ©2005 Silberschatz, Galvin, and Gagne. Many slides generated from my lecture notes by Kubiatowicz.

Correctness for systems with concurrent threads

- If dispatcher can schedule threads in any way, programs must work under all circumstances
  - Can you test for this?
  - How can you know if your program works?
- Independent Threads:
  - No state shared with other threads
  - Deterministic ⇒ Input state determines results
  - Reproducible ⇒ Can recreate Starting Conditions, I/O
  - Scheduling order doesn't matter (if `switch()` works!!!)
- Cooperating Threads:
  - Shared State between multiple threads
  - Non-deterministic
  - Non-reproducible
- Non-deterministic and Non-reproducible means that bugs can be intermittent
  - Sometimes called "Heisenbugs"

Interactions Complicate Debugging

- Is any program truly independent?
  - Every process shares the file system, OS resources, network, etc
  - Extreme example: buggy device driver causes thread A to crash "independent thread" B
- You probably don't realize how much you depend on reproducibility:
  - Example: Evil C compiler
    - » Modifies files behind your back by inserting errors into C program unless you insert debugging code
  - Example: Debugging statements can overrun stack
- Non-deterministic errors are really difficult to find
  - Example: Memory layout of kernel+user programs
    - » depends on scheduling, which depends on timer/other things
    - » Original UNIX had a bunch of non-deterministic errors
  - Example: Something which does interesting I/O
    - » User typing of letters used to help generate secure keys

Why allow cooperating threads?

- People cooperate; computers help/enhance people's lives, so computers must cooperate
  - By analogy, the non-reproducibility/non-determinism of people is a notable problem for "carefully laid plans"
- Advantage 1: Share resources
  - One computer, many users
  - One bank balance, many ATMs
    - » What if ATMs were only updated at night?
  - Embedded systems (robot control: coordinate arm & hand)
- Advantage 2: Speedup
  - Overlap I/O and computation
    - » Many different file systems do read-ahead
  - Multiprocessors – chop up program into parallel pieces
- Advantage 3: Modularity
  - More important than you might think
  - Chop large problem up into simpler pieces
    - » To compile, for instance, gcc calls cpp | cc1 | cc2 | as | ld
    - » Makes system easier to extend

High-level Example: Web Server



- Server must handle many requests
- Non-cooperating version:

```
serverLoop() {
    con = AcceptCon();
    ProcessFork(ServiceWebPage(),con);
}
```

- What are some disadvantages of this technique?

Threaded Web Server

- Now, use a single process
- Multithreaded (cooperating) version:

```
serverLoop() {
    connection = AcceptCon();
    ThreadFork(ServiceWebPage(),connection);
}
```

- Looks almost the same, but has many advantages:
  - Can share file caches kept in memory, results of CGI scripts, other things
  - Threads are *much* cheaper to create than processes, so this has a lower per-request overhead
- Question: would a user-level (say one-to-many) thread package make sense here?
  - When one request blocks on disk, all block…
- What about Denial of Service attacks or digg / Slash-dot effects?

Thread Pools

- Problem with previous version: Unbounded Threads
  - When web-site becomes too popular – throughput sinks
- Instead, allocate a bounded "pool" of worker threads, representing the maximum level of multiprogramming




```
master() {
   allocThreads(worker,queue);
   while(TRUE) {
      con=AcceptCon();
      Enqueue(queue,con);
      wakeUp(queue);
   }
}
```

```
worker(queue) {
   while(TRUE) {
      con=Dequeue(queue);
      if (con==null)
         sleepOn(queue);
      else
         ServiceWebPage(con);
   }
}
```


ATM Bank Server



- ATM server problem:
  - Service a set of requests
  - Do so without corrupting database
  - Don't hand out too much money

ATM bank server example

- Suppose we wanted to implement a server process to handle requests from an ATM network:

```
BankServer() {
   while (TRUE) {
      ReceiveRequest(&op, &acctId, &amount);
      ProcessRequest(op, acctId, amount);
   }
}
ProcessRequest(op, acctId, amount) {
   if (op == deposit) Deposit(acctId, amount);
   else if …
}
Deposit(acctId, amount) {
   acct = GetAccount(acctId); /* may use disk I/O */
   acct->balance += amount;
   StoreAccount(acct); /* Involves disk I/O */
}
```

- How could we speed this up?
  - More than one request being processed at once
  - Event driven (overlap computation and I/O)
  - Multiple threads (multi-proc, or overlap comp and I/O)

Event Driven Version of ATM server

- Suppose we only had one CPU
  - Still like to overlap I/O with computation
  - Without threads, we would have to rewrite in event-driven style
- Example

```
BankServer() {
   while(TRUE) {
      event = WaitForNextEvent();
      if (event == ATMRequest)
         StartOnRequest();
      else if (event == AcctAvail)
         ContinueRequest();
      else if (event == AcctStored)
         FinishRequest();
   }
}
```

  - What if we missed a blocking I/O step?
  - What if we have to split code into hundreds of pieces which could be blocking?
  - This technique is used for graphical programming

Can Threads Make This Easier?

- Threads yield overlapped I/O and computation without "deconstructing" code into non-blocking fragments
  - One thread per request
- Requests proceeds to completion, blocking as required:

```
Deposit(acctId, amount) {
  acct = GetAccount(actId); /* May use disk I/O */
  acct->balance += amount;
  StoreAccount(acct);      /* Involves disk I/O */
}
```

- Unfortunately, shared state can get corrupted:

Thread 1	Thread 2
`load r1, acct->balance`	
	`load r1, acct->balance`
	`add r1, amount2`
	`store r1, acct->balance`
`add r1, amount1`	
`store r1, acct->balance`	

Review: Multiprocessing vs Multiprogramming

- What does it mean to run two threads "concurrently"?
  - Scheduler is free to run threads in any order and interleaving: FIFO, Random, …
  - Dispatcher can choose to run each thread to completion or time-slice in big chunks or small chunks



- Also recall: Hyperthreading
  - Possible to interleave threads on a per-instruction basis
  - Keep this in mind for our examples (like multiprocessing)

Problem is at the lowest level

- Most of the time, threads are working on separate data, so scheduling doesn't matter:

Thread A	Thread B
x = 1;	y = 2;

- However, What about (Initially, y = 12):

Thread A	Thread B
x = 1;	y = 2;
x = y+1;	y = y*2;

  - What are the possible values of x?
- Or, what are the possible values of x below?

Thread A	Thread B
x = 1;	x = 2;

  - X could be 1 or 2 (non-deterministic!)
  - Could even be 3 for serial processors:
    - » Thread A writes 0001, B writes 0010.
    - » Scheduling order ABABABBA yields 3!

Atomic Operations

- To understand a concurrent program, we need to know what the underlying indivisible operations are!
- **Atomic Operation**: an operation that always runs to completion or not at all
  - It is *indivisible:* it cannot be stopped in the middle and state cannot be modified by someone else in the middle
  - Fundamental building block – if no atomic operations, then have no way for threads to work together
- On most machines, memory references and assignments (i.e. loads and stores) of words are atomic
  - Consequently – weird example that produces "3" on previous slide can't happen
- Many instructions are not atomic
  - Double-precision floating point store often not atomic
  - VAX and IBM 360 had an instruction to copy a whole array

Correctness Requirements

- Threaded programs must work for all interleavings of thread instruction sequences
  - Cooperating threads inherently non-deterministic and non-reproducible
  - Really hard to debug unless carefully designed!
- Example: Therac-25
  - Machine for radiation therapy
    - » Software control of electron accelerator and electron beam/ Xray production
    - » Software control of dosage
  - Software errors caused the death of several patients
    - » A series of race conditions on shared variables and poor software design
    - » "They determined that data entry speed during editing was the key factor in producing the error condition: If the prescription data was edited at a fast pace, the overdose occurred."



Figure 1. Typical Therac-25 facility

Space Shuttle Example

- Original Space Shuttle launch aborted 20 minutes before scheduled launch
- Shuttle has five computers:
  - Four run the "Primary Avionics Software System" (PASS)
    - » Asynchronous and real-time
    - » Runs all of the control systems
    - » Results synchronized and compared every 3 to 4 ms
  - The Fifth computer is the "Backup Flight System" (BFS)
    - » stays synchronized in case it is needed
    - » Written by completely different team than PASS



- Countdown aborted because BFS disagreed with PASS
  - A 1/67 chance that PASS was out of sync one cycle
  - Bug due to modifications in initialization code of PASS
    - » A delayed init request placed into timer queue
    - » As a result, timer queue not empty at expected time to force use of hardware clock
  - Bug not found during extensive simulation

Another Concurrent Program Example

- Two threads, A and B, compete with each other
  - One tries to increment a shared counter
  - The other tries to decrement the counter

Thread A	Thread B

i = 0;
while (i < 10)
  i = i + 1;
printf("A wins!");
	i = 0;
	while (i > -10)
	  i = i - 1;
	printf("B wins!");

- Assume that memory loads and stores are atomic, but incrementing and decrementing are *not* atomic
- Who wins? Could be either
- Is it guaranteed that someone wins? Why or why not?
- What if both threads have their own CPU running at same speed? Is it guaranteed that it goes on forever?

Hand Simulation Multiprocessor Example

- Inner loop looks like this:

Thread A		Thread B	
r1=0	load r1, M[i]		
		r1=0	load r1, M[i]
r1=1	add r1, r1, 1		
		r1=-1	sub r1, r1, 1
M[i]=1	store r1, M[i]		
		M[i]=-1	store r1, M[i]

- Hand Simulation:
  - And we're off. A gets off to an early start
  - B says "hmph, better go fast" and tries really hard
  - A goes ahead and writes "1"
  - B goes and writes "-1"
  - A says "HUH??? I could have sworn I put a 1 there"
- Could this happen on a uniprocessor?
  - Yes! Unlikely, but if you are depending on it not happening, it will and your system will break…

Administrivia

- Don't Forget New Section!
  - Thursday 12-1, 320 Soda Hall
  - Need to know your TA!
- Sorry about HW 1
  - Got a little longer than we expected
  - Due next Monday! (HW 2 not handed out until Monday)
- No class on Monday! (Holiday)

Motivation: "Too much milk"

- Great thing about OS's – analogy between problems in OS and problems in real life
  - Help you understand real life problems better
  - But, computers are much stupider than people
- Example: People need to coordinate:

Time	Person A	Person B
3:00	Look in Fridge. Out of milk	
3:05	Leave for store	
3:10	Arrive at store	Look in Fridge. Out of milk
3:15	Buy milk	Leave for store
3:20	Arrive home, put milk away	Arrive at store
3:25		Buy milk
3:30		Arrive home, put milk away

Definitions

- **Synchronization**: using atomic operations to ensure cooperation between threads
  - For now, only loads and stores are atomic
  - We are going to show that its hard to build anything useful with only reads and writes
- **Mutual Exclusion**: ensuring that only one thread does a particular thing at a time
  - One thread *excludes* the other while doing its task
- **Critical Section**: piece of code that only one thread can execute at once. Only one thread at a time will get into this section of code.
  - Critical section is the result of mutual exclusion
  - Critical section and mutual exclusion are two ways of describing the same thing.

More Definitions

- **Lock**: prevents someone from doing something
  - Lock before entering critical section and before accessing shared data
  - Unlock when leaving, after accessing shared data
  - Wait if locked
    - » Important idea: all synchronization involves waiting
- For example: fix the milk problem by putting a key on the refrigerator
  - Lock it and take key if you are going to go buy milk
  - Fixes too much: roommate angry if only wants OJ



  - Of Course – We don't know how to make a lock yet

Too Much Milk: Correctness Properties

- Need to be careful about correctness of concurrent programs, since non-deterministic
  - Always write down behavior first
  - Impulse is to start coding first, then when it doesn't work, pull hair out
  - Instead, think first, then code
- What are the correctness properties for the "Too much milk" problem???
  - Never more than one person buys
  - Someone buys if needed
- Restrict ourselves to use only atomic load and store operations as building blocks

Too Much Milk: Solution #1

- Use a note to avoid buying too much milk:
  - Leave a note before buying (kind of "lock")
  - Remove note after buying (kind of "unlock")
  - Don't buy if note (wait)
- Suppose a computer tries this (remember, only memory read/write are atomic):

```
if (noMilk) {
   if (noNote) {
      leave Note;
      buy milk;
      remove note;
   }
}
```



- Result?
  - Still too much milk **but only occasionally!**
  - Thread can get context switched after checking milk and note but before buying milk!
- Solution makes problem worse since fails **intermittently**
  - Makes it really hard to debug…
  - Must work despite what the dispatcher does!

Too Much Milk: Solution #1½

- Clearly the Note is not quite blocking enough
  - Let's try to fix this by placing note first
- Another try at previous solution:

```
leave Note;
if (noMilk) {
   if (noNote) {
      leave Note;
      buy milk;
   }
}
remove note;
```

- What happens here?
  - Well, with human, probably nothing bad
  - With computer: no one ever buys milk

Too Much Milk Solution #2

- How about labeled notes?
  - Now we can leave note before checking
- Algorithm looks like this:

<u>Thread A</u>

```
leave note A;
if (noNote B) {
   if (noMilk) {
      buy Milk;
   }
}
remove note A;
```

<u>Thread B</u>

```
leave note B;
if (noNoteA) {
   if (noMilk) {
      buy Milk;
   }
}
remove note B;
```

- Does this work?
- Possible for neither thread to buy milk
  - Context switches at exactly the wrong times can lead each to think that the other is going to buy
- Really insidious:
  - **Extremely unlikely** that this would happen, but will at worse possible time
  - Probably something like this in UNIX

Too Much Milk Solution #2: problem!



- *I'm* not getting milk, *You're* getting milk
- This kind of lockup is called "starvation!"

Too Much Milk Solution #3

- Here is a possible two-note solution:

Thread A
```
leave note A;
while (note B) { //X
    do nothing;
}
if (noMilk) {
    buy milk;
}
remove note A;
```

Thread B
```
leave note B;
if (noNote A) { //Y
    if (noMilk) {
        buy milk;
    }
}
remove note B;
```

- Does this work? Yes. Both can guarantee that:
  - It is safe to buy, or
  - Other will buy, ok to quit
- At X:
  - if no note B, safe for A to buy,
  - otherwise wait to find out what will happen
- At Y:
  - if no note A, safe for B to buy
  - Otherwise, A is either buying or waiting for B to quit

Solution #3 discussion

- Our solution protects a single "Critical-Section" piece of code for each thread:

```
if (noMilk) {
    buy milk;
}
```

- Solution #3 works, but it's really unsatisfactory
  - Really complex – even for this simple an example
    - » Hard to convince yourself that this really works
  - A's code is different from B's – what if lots of threads?
    - » Code would have to be slightly different for each thread
  - While A is waiting, it is consuming CPU time
    - » This is called "busy-waiting"
- There's a better way
  - Have hardware provide better (higher-level) primitives than atomic load and store
  - Build even higher-level programming abstractions on this new hardware support

Too Much Milk: Solution #4

- Suppose we have some sort of implementation of a lock (more in a moment).
  - `Lock.Acquire()` – wait until lock is free, then grab
  - `Lock.Release()` – Unlock, waking up anyone waiting
  - These must be atomic operations – if two threads are waiting for the lock and both see it's free, only one succeeds to grab the lock
- Then, our milk problem is easy:

```
milklock.Acquire();
if (nomilk)
    buy milk;
milklock.Release();
```

- Once again, section of code between `Acquire()` and `Release()` called a "Critical Section"
- Of course, you can make this even simpler: suppose you are out of ice cream instead of milk
  - Skip the test since you always need more ice cream.

Where are we going with synchronization?

Programs	Shared Programs
Higher-level API	Locks Semaphores Monitors Send/Receive
Hardware	Load/Store Disable Ints Test&Set Comp&Swap

- We are going to implement various higher-level synchronization primitives using atomic operations
  - Everything is pretty painful if only atomic primitives are load and store
  - Need to provide primitives useful at user-level

How to implement Locks?

- Lock: prevents someone from doing something
  - Lock before entering critical section and before accessing shared data
  - Unlock when leaving, after accessing shared data
  - Wait if locked
    - » Important idea: all synchronization involves waiting
    - » Should *sleep* if waiting for a long time
- Atomic Load/Store: get solution like Milk #3
  - Looked at this last lecture
  - Pretty complex and error prone
- Hardware Lock instruction
  - Is this a good idea?
  - What about putting a task to sleep?
    - » How do you handle the interface between the hardware and scheduler?
  - Complexity?
    - » Done in the Intel 432
    - » Each feature makes hardware more complex and slow

Naïve use of Interrupt Enable/Disable

- How can we build multi-instruction atomic operations?
  - Recall: dispatcher gets control in two ways.
    - » Internal: Thread does something to relinquish the CPU
    - » External: Interrupts cause dispatcher to take CPU
  - On a uniprocessor, can avoid context-switching by:
    - » Avoiding internal events (although virtual memory tricky)
    - » Preventing external events by disabling interrupts
- Consequently, naïve Implementation of locks:

```
LockAcquire { disable Ints; }
LockRelease { enable Ints; }
```

- Problems with this approach:
  - Can't let user do this! Consider following:

```
LockAcquire();
While(TRUE) {;}
```

  - Real-Time system—no guarantees on timing!
    - » Critical Sections might be arbitrarily long
  - What happens with I/O or other important events?
    - » "Reactor about to meltdown. Help?"

Better Implementation of Locks by Disabling Interrupts

- Key idea: maintain a lock variable and impose mutual exclusion only during operations on that variable

```
int value = FREE;
```



```
Acquire() {
  disable interrupts;
  if (value == BUSY) {
    put thread on wait queue;
    Go to sleep();
    // Enable interrupts?
  } else {
    value = BUSY;
  }
  enable interrupts;
}
```

```
Release() {
  disable interrupts;
  if (anyone on wait queue) {
    take thread off wait queue
    Place on ready queue;
  } else {
    value = FREE;
  }
  enable interrupts;
}
```

New Lock Implementation: Discussion

- Why do we need to disable interrupts at all?
  - Avoid interruption between checking and setting lock value
  - Otherwise two threads could think that they both have lock

```
Acquire() {
   disable interrupts;
   if (value == BUSY) {
      put thread on wait queue;
      Go to sleep();
      // Enable interrupts?
   } else {
      value = BUSY;
   }
   enable interrupts;
}
```

Critical Section

- Note: unlike previous solution, the critical section (inside Acquire()) is very short
  - User of lock can take as long as they like in their own critical section: doesn't impact global machine behavior
  - Critical interrupts taken in time!

Interrupt re-enable in going to sleep

- What about re-enabling ints when going to sleep?

Enable Position
Enable Position
Enable Position

```
Acquire() {
   disable interrupts;
   if (value == BUSY) {
      put thread on wait queue;
      Go to sleep();
   } else {
      value = BUSY;
   }
   enable interrupts;
}
```


How to Re-enable After Sleep()?

- In scheduler, since interrupts are disabled when you call sleep:
  - Responsibility of the next thread to re-enable ints
  - When the sleeping thread wakes up, returns to acquire and re-enables interrupts

<u>Thread A</u> <u>Thread B</u>

```
     .
     .
disable ints
   sleep      context switch →
                              sleep return
                               enable ints
                                    .
                                    .
                                    .
                               disable int
                                  sleep
sleep return ← context switch
 enable ints
     .
     .
```


Atomic Read-Modify-Write instructions

- Problems with previous solution:
  - Can't give lock implementation to users
  - Doesn't work well on multiprocessor
    - » Disabling interrupts on all processors requires messages and would be very time consuming
- Alternative: atomic instruction sequences
  - These instructions read a value from memory and write a new value atomically
  - Hardware is responsible for implementing this correctly
    - » on both uniprocessors (not too hard)
    - » and multiprocessors (requires help from cache coherence protocol)
  - Unlike disabling interrupts, can be used on both uniprocessors and multiprocessors

Examples of Read-Modify-Write

- ```
  test&set (&address) {       /* most architectures */
      result = M[address];
      M[address] = 1;
      return result;
  }
  ```
- ```
  swap (&address, register) { /* x86 */
      temp = M[address];
      M[address] = register;
      register = temp;
  }
  ```
- ```
  compare&swap (&address, reg1, reg2) { /* 68000 */
      if (reg1 == M[address]) {
          M[address] = reg2;
          return success;
      } else {
          return failure;
      }
  }
  ```
- ```
  load-linked&store conditional(&address) {
      /* R4000, alpha */
      loop:
          ll r1, M[address];
          movi r2, 1;           /* Can do arbitrary comp */
          sc r2, M[address];
          beqz r2, loop;
  }
  ```


Implementing Locks with test&set

- Another flawed, but simple solution:

```
int value = 0; // Free
Acquire() {
   while (test&set(value)); // while busy
}
Release() {
   value = 0;
}
```

- Simple explanation:
  - If lock is free, test&set reads 0 and sets value=1, so lock is now busy. It returns 0 so while exits.
  - If lock is busy, test&set reads 1 and sets value=1 (no change). It returns 1, so while loop continues
  - When we set value = 0, someone else can get lock
- **Busy-Waiting**: thread consumes cycles while waiting

Problem: Busy-Waiting for Lock

- Positives for this solution
  - Machine can receive interrupts
  - User code can use this lock
  - Works on a multiprocessor
- Negatives
  - This is very inefficient because the busy-waiting thread will consume cycles waiting
  - Waiting thread may take cycles away from thread holding lock (no one wins!)
  - **Priority Inversion**: If busy-waiting thread has higher priority than thread holding lock ⇒ no progress!
- Priority Inversion problem with original Martian rover
- For semaphores and monitors, waiting thread may wait for an arbitrary length of time!
  - Thus even if busy-waiting was OK for locks, definitely not ok for other primitives
  - Homework/exam solutions should not have busy-waiting!

Better Locks using test&set

- Can we build test&set locks without busy-waiting?
  - Can't entirely, but can minimize!
  - Idea: only busy-wait to atomically check lock value

```
int guard = 0;
int value = FREE;
```



```
Acquire() {
   // Short busy-wait time
   while (test&set(guard));
   if (value == BUSY) {
      put thread on wait queue;
      go to sleep() & guard = 0;
   } else {
      value = BUSY;
      guard = 0;
   }
}
```

```
Release() {
   // Short busy-wait time
   while (test&set(guard));
   if anyone on wait queue {
      take thread off wait queue
      Place on ready queue;
   } else {
      value = FREE;
   }
   guard = 0;
```

- Note: sleep has to be sure to reset the guard variable
  - Why can't we do it just before or just after the sleep?

Higher-level Primitives than Locks

- Goal of last couple of lectures:
  - What is the right abstraction for synchronizing threads that share memory?
  - Want as high a level primitive as possible
- Good primitives and practices important!
  - Since execution is not entirely sequential, really hard to find bugs, since they happen rarely
  - UNIX is pretty stable now, but up until about mid-80s (10 years after started), systems running UNIX would crash every week or so – concurrency bugs
- Synchronization is a way of coordinating multiple concurrent activities that are using shared state
  - This lecture and the next presents a couple of ways of structuring the sharing

Semaphores



- Semaphores are a kind of generalized lock
  - First defined by Dijkstra in late 60s
  - Main synchronization primitive used in original UNIX
- Definition: a Semaphore has a non-negative integer value and supports the following two operations:
  - P(): an atomic operation that waits for semaphore to become positive, then decrements it by 1
    - » Think of this as the wait() operation
  - V(): an atomic operation that increments the semaphore by 1, waking up a waiting P, if any
    - » This of this as the signal() operation
  - Note that P() stands for "*proberen*" (to test) and V() stands for "*verhogen*" (to increment) in Dutch

Semaphores Like Integers Except

- Semaphores are like integers, except
  - No negative values
  - Only operations allowed are P and V – can't read or write value, except to set it initially
  - Operations must be atomic
    - » Two P's together can't decrement value below zero
    - » Similarly, thread going to sleep in P won't miss wakeup from V – even if they both happen at same time
- Semaphore from railway analogy
  - Here is a semaphore initialized to 2 for resource control:



Two Uses of Semaphores

- Mutual Exclusion (initial value = 1)
  - Also called "Binary Semaphore".
  - Can be used for mutual exclusion:

```
semaphore.P();
// Critical section goes here
semaphore.V();
```

- Scheduling Constraints (initial value = 0)
  - Locks are fine for mutual exclusion, but what if you want a thread to wait for something?
  - Example: suppose you had to implement ThreadJoin which must wait for thread to terminiate:

```
Initial value of semaphore = 0
ThreadJoin {
   semaphore.P();
}
ThreadFinish {
   semaphore.V();
}
```

Producer-consumer with a bounded buffer

- Problem Definition
  - Producer puts things into a shared buffer
  - Consumer takes them out
  - Need synchronization to coordinate producer/consumer
- Don't want producer and consumer to have to work in lockstep, so put a fixed-size buffer between them
  - Need to synchronize access to this buffer
  - Producer needs to wait if buffer is full
  - Consumer needs to wait if buffer is empty
- Example 1: GCC compiler
  - cpp | cc1 | cc2 | as | ld
- Example 2: Coke machine
  - Producer can put limited number of cokes in machine
  - Consumer can't take cokes out if machine is empty

Correctness constraints for solution

- Correctness Constraints:
  - Consumer must wait for producer to fill buffers, if none full (scheduling constraint)
  - Producer must wait for consumer to empty buffers, if all full (scheduling constraint)
  - Only one thread can manipulate buffer queue at a time (mutual exclusion)
- Remember why we need mutual exclusion
  - Because computers are stupid
  - Imagine if in real life: the delivery person is filling the machine and somebody comes up and tries to stick their money into the machine
- General rule of thumb:
  Use a separate semaphore for each constraint
  - `Semaphore fullBuffers; // consumer's constraint`
  - `Semaphore emptyBuffers;// producer's constraint`
  - `Semaphore mutex;       // mutual exclusion`

Full Solution to Bounded Buffer

```
Semaphore fullBuffer = 0; // Initially, no coke
Semaphore emptyBuffers = numBuffers;
                          // Initially, num empty slots
Semaphore mutex = 1;      // No one using machine

Producer(item) {
   emptyBuffers.P();      // Wait until space
   mutex.P();             // Wait until buffer free
   Enqueue(item);
   mutex.V();
   fullBuffers.V();       // Tell consumers there is
                          // more coke
}
Consumer() {
   fullBuffers.P();       // Check if there's a coke
   mutex.P();             // Wait until machine free
   item = Dequeue();
   mutex.V();
   emptyBuffers.V();      // tell producer need more
   return item;
}
```


Discussion about Solution

- Why asymmetry?
  - Producer does: `emptyBuffer.P(), fullBuffer.V()`
  - Consumer does: `fullBuffer.P(), emptyBuffer.V()`
- Is order of P's important?
- Is order of V's important?
- What if we have 2 producers or 2 consumers?
  - Do we need to change anything?

Motivation for Monitors and Condition Variables

- Semaphores are a huge step up; just think of trying to do the bounded buffer with only loads and stores
  - Problem is that semaphores are dual purpose:
    - » They are used for both mutex and scheduling constraints
    - » Example: the fact that flipping of P's in bounded buffer gives deadlock is not immediately obvious. How do you prove correctness to someone?
- Cleaner idea: Use *locks* for mutual exclusion and *condition variables* for scheduling constraints
- Definition: Monitor: a lock and zero or more condition variables for managing concurrent access to shared data
  - Some languages like Java provide this natively
  - Most others use actual locks and condition variables

Monitor with Condition Variables



- Lock: the lock provides mutual exclusion to shared data
  - Always acquire before accessing shared data structure
  - Always release after finishing with shared data
  - Lock initially free
- Condition Variable: a queue of threads waiting for something *inside* a critical section
  - Key idea: make it possible to go to sleep inside critical section by atomically releasing lock at time we go to sleep
  - Contrast to semaphores: Can't wait inside critical section

Simple Monitor Example

- Here is an (infinite) synchronized queue

```
Lock lock;
Condition dataready;
Queue queue;

AddToQueue(item) {
   lock.Acquire();          // Get Lock
   queue.enqueue(item);     // Add item
   dataready.signal();      // Signal any waiters
   lock.Release();          // Release Lock
}

RemoveFromQueue() {
   lock.Acquire();          // Get Lock
   while (queue.isEmpty()) {
      dataready.wait(&lock); // If nothing, sleep
   }
   item = queue.dequeue();  // Get next item
   lock.Release();          // Release Lock
   return(item);
}
```


Summary

- Important concept: Atomic Operations
  - An operation that runs to completion or not at all
  - These are the primitives on which to construct various synchronization primitives
- Talked about hardware atomicity primitives:
  - Disabling of Interrupts, test&set, swap, comp&swap, load-linked/store conditional
- Showed several constructions of Locks
  - Must be very careful not to waste/tie up machine resources
    - » Shouldn't disable interrupts for long
    - » Shouldn't spin wait for long
  - Key idea: Separate lock variable, use hardware mechanisms to protect modifications of that variable
- Talked about Semaphores, Monitors, and Condition Variables
  - Higher level constructs that are harder to "screw up"