


CSI62
Operating Systems and
Systems Programming
Lecture 15

Demand Paging (Finished)

October 16th, 2017
Ion Stoica
<http://cs162.eecs.berkeley.edu>

Management & Access to the Memory Hierarchy



Recall: Some following questions

- During a page fault, where does the OS get a free frame?
 - Keeps a free list
 - Unix runs a "reaper" if memory gets too full
 - » Schedule dirty pages to be written back on disk
 - » Zero (clean) pages which haven't been accessed in a while
 - As a last resort, evict a dirty page first
- How can we organize these mechanisms?
 - Work on the replacement policy
- How many page frames/process?
 - Like thread scheduling, need to "schedule" memory resources:
 - » Utilization? fairness? priority?
 - Allocation of disk paging bandwidth

10/16/17

CS162 @UCB Fall 2017

Lec 15.3

Demand Paging Cost Model

- Since Demand Paging like caching, can compute average access time! ("Effective Access Time")
 - $EAT = Hit\ Rate \times Hit\ Time + Miss\ Rate \times Miss\ Time$
 - $EAT = Hit\ Time + Miss\ Rate \times Miss\ Penalty$
- Example:
 - Memory access time = 200 nanoseconds
 - Average page-fault service time = 8 milliseconds
 - Suppose p = Probability of miss, $1-p$ = Probability of hit
 - Then, we can compute EAT as follows:

$$EAT = 200ns + p \times 8\ ms$$

$$= 200ns + p \times 8,000,000ns$$
- If one access out of 1,000 causes a page fault, then $EAT = 8.2\ \mu s$:
 - This is a slowdown by a factor of 40!
- What if want slowdown by less than 10%?
 - $200ns \times 1.1 < EAT \Rightarrow p < 2.5 \times 10^{-6}$
 - This is about 1 page fault in 400,000!

10/16/17

CS162 @UCB Fall 2017

Lec 15.4

What Factors Lead to Misses?

- **Compulsory Misses:**
 - Pages that have never been paged into memory before
 - How might we remove these misses?
 - » Prefetching: loading them into memory before needed
 - » Need to predict future somehow! More later
- **Capacity Misses:**
 - Not enough memory. Must somehow increase available memory size.
 - Can we do this?
 - » One option: Increase amount of DRAM (not quick fix!)
 - » Another option: If multiple processes in memory: adjust percentage of memory allocated to each one!
- **Conflict Misses:**
 - Technically, conflict misses don't exist in virtual memory, since it is a "fully-associative" cache
- **Policy Misses:**
 - Caused when pages were in memory, but kicked out prematurely because of the replacement policy
 - How to fix? Better replacement policy

10/16/17

CSI62 @UCB Fall 2017

Lec 15.5

Page Replacement Policies

- Why do we care about Replacement Policy?
 - Replacement is an issue with any cache
 - Particularly important with pages
 - » The cost of being wrong is high: must go to disk
 - » Must keep important pages in memory, not toss them out
- **FIFO (First In, First Out)**
 - Throw out oldest page. Be fair – let every page live in memory for same amount of time.
 - Bad – throws out heavily used pages instead of infrequently used
- **MIN (Minimum):**
 - Replace page that won't be used for the longest time
 - Great, but can't really know future...
 - Makes good comparison case, however
- **RANDOM:**
 - Pick random page for every replacement
 - Typical solution for TLB's. Simple hardware
 - Pretty unpredictable – makes it hard to make real-time guarantees

10/16/17

CSI62 @UCB Fall 2017

Lec 15.6

Replacement Policies (Con't)

- **LRU (Least Recently Used):**
 - Replace page that hasn't been used for the longest time
 - Programs have locality, so if something not used for a while, unlikely to be used in the near future.
 - Seems like LRU should be a good approximation to MIN.
- How to implement LRU? Use a list!

 - On each use, remove page from list and place at head
 - LRU page is at tail
- Problems with this scheme for paging?
 - Need to know immediately when each page used so that can change position in list...
 - Many instructions for each hardware access
- In practice, people **approximate** LRU (more later)

10/16/17

CSI62 @UCB Fall 2017

Lec 15.7

Example: FIFO

- Suppose we have 3 page frames, 4 virtual pages, and following reference stream:
 - A B C A B D A D B C B
- Consider FIFO Page replacement:

Ref:	A	B	C	A	B	D	A	D	B	C	B
Page:											
1	A					D				C	
2		B					A				
3			C						B		

- FIFO: 7 faults
- When referencing D, replacing A is bad choice, since need A again right away

10/16/17

CSI62 @UCB Fall 2017

Lec 15.8

Example: MIN

- Suppose we have the same reference stream:
 - A B C A B D A D B C B
- Consider MIN Page replacement:

Ref:	A	B	C	A	B	D	A	D	B	C	B
Page:											
1	A									C	
2		B									
3			C			D					

- MIN: 5 faults
 - Where will D be brought in? Look for page not referenced farthest in future
- What will LRU do?
 - Same decisions as MIN here, but won't always be true!

10/16/17

CS162 @UCB Fall 2017

Lec 15.9

When will LRU perform badly?

- Consider the following: A B C D A B C D A B C D
- LRU Performs as follows (same as FIFO here):

Ref:	A	B	C	D	A	B	C	D	A	B	C	D
Page:												
1	A			D			C			B		
2		B			A			D			C	
3			C			B			A			D

- Every reference is a page fault!

10/16/17

CS162 @UCB Fall 2017

Lec 15.10

When will LRU perform badly?

- Consider the following: A B C D A B C D A B C D
- LRU Performs as follows (same as FIFO here):

Ref:	A	B	C	D	A	B	C	D	A	B	C	D
Page:												
1	A			D			C			B		
2		B			A			D			C	
3			C			B			A			D

- Every reference is a page fault!

- MIN Does much better:


Ref:	A	B	C	D	A	B	C	D	A	B	C	D
Page:												
1	A									B		
2		B					C					
3			C	D								

10/16/17

CS162 @UCB Fall 2017

Lec 15.11

Graph of Page Faults Versus The Number of Frames



- One desirable property: When you add memory the miss rate drops
 - Does this always happen?
 - Seems like it should, right?
- No: Bélády's anomaly
 - Certain replacement algorithms (FIFO) don't have this obvious property!

10/16/17

CS162 @UCB Fall 2017

Lec 15.12

Adding Memory Doesn't Always Help Fault Rate

- Does adding memory reduce number of page faults?
 - Yes for LRU and MIN
 - Not necessarily for FIFO! (Called Bélády's anomaly)

Ref. Page:	A	B	C	D	A	B	E	A	B	C	D	E
1	A			D			E					
2		B			A					C		
3			C			B					D	

Ref. Page:	A	B	C	D	A	B	E	A	B	C	D	E
1	A						E				D	
2		B						A				E
3			C						B			
4				D						C		

- After adding memory:
 - With FIFO, contents can be completely different
 - In contrast, with LRU or MIN, contents of memory with X pages are a subset of contents with $X+1$ Page

10/16/17

CS162 @UCB Fall 2017

Lec 15.13

Implementing LRU


- Perfect:
 - Timestamp page on each reference
 - Keep list of pages ordered by time of reference
 - Too expensive to implement in reality for many reasons
- Clock Algorithm:** Arrange physical pages in circle with single clock hand
 - Approximate LRU (approximation to approximation to MIN)
 - Replace an old page, not the oldest page
- Details:
 - Hardware "use" bit per physical page:
 - Hardware sets use bit on each reference
 - If use bit isn't set, means not referenced in a long time
 - Some hardware sets use bit in the TLB; you have to copy this back to page table entry when TLB entry gets replaced
 - On page fault:
 - Advance clock hand (not real time)
 - Check use bit: 1 → used recently; clear and leave alone
 - 0 → selected candidate for replacement
 - Will always find a page or loop forever?
 - Even if all use bits set, will eventually loop around ⇒ FIFO

10/16/17

CS162 @UCB Fall 2017

Lec 15.14

Clock Algorithm: Not Recently Used



- What if hand moving slowly?
 - Good sign or bad sign?
 - Not many page faults and/or find page quickly
- What if hand is moving quickly?
 - Lots of page faults and/or lots of reference bits set
- One way to view clock algorithm:
 - Crude partitioning of pages into two groups: young and old
 - Why not partition into more than 2 groups?

10/16/17

CS162 @UCB Fall 2017

Lec 15.15

N^{th} Chance version of Clock Algorithm

- N^{th} chance algorithm:** Give page N chances
 - OS keeps counter per page: # sweeps
 - On page fault, OS checks use bit:
 - 1 → clear use and also clear counter (used in last sweep)
 - 0 → increment counter; if count= N , replace page
 - Means that clock hand has to sweep by N times without page being used before page is replaced
- How do we pick N ?
 - Why pick large N ? Better approximation to LRU
 - If $N \sim 1K$, really good approximation
 - Why pick small N ? More efficient
 - Otherwise might have to look a long way to find free page
- What about dirty pages?
 - Takes extra overhead to replace a dirty page, so give dirty pages an extra chance before replacing?
 - Common approach:
 - Clean pages, use $N=1$
 - Dirty pages, use $N=2$ (and write back to disk when $N=1$)

10/16/17

CS162 @UCB Fall 2017

Lec 15.16

Clock Algorithms: Details

- Which bits of a PTE entry are useful to us?
 - **Use:** Set when page is referenced; cleared by clock algorithm
 - **Modified:** set when page is modified, cleared when page written to disk
 - **Valid:** ok for program to reference this page
 - **Read-only:** ok for program to read page, but not modify
 - » For example for catching modifications to code pages!
- Do we really need hardware-supported “modified” bit?
 - No. Can emulate it (BSD Unix) using read-only bit
 - » Initially, mark all pages as read-only, even data pages
 - » On write, trap to OS. OS sets software “modified” bit, and marks page as read-write.
 - » Whenever page comes back in from disk, mark read-only

10/16/17

CS162 @UCB Fall 2017

Lec 15.17

Clock Algorithms Details (continued)


- Do we really need a hardware-supported “use” bit?
 - No. Can emulate it similar to above:
 - » Mark all pages as invalid, even if in memory
 - » On read to invalid page, trap to OS
 - » OS sets use bit, and marks page read-only
 - Get modified bit in same way as previous:
 - » On write, trap to OS (either invalid or read-only)
 - » Set use and modified bits, mark page read-write
 - When clock hand passes by, reset use and modified bits and mark page as invalid again
- Remember, however, that clock is just an approximation of LRU
 - Can we do a better approximation, given that we have to take page faults on some reads and writes to collect use information?
 - Need to identify an old page, not oldest page!
 - Answer: second chance list

10/16/17

CS162 @UCB Fall 2017

Lec 15.18

Second-Chance List Algorithm (VAX/VMS)



- Split memory in two: Active list (RW), SC list (Invalid)
- Access pages in Active list at full speed
- Otherwise, Page Fault
 - Always move overflow page from end of Active list to front of Second-chance list (SC) and mark invalid
 - Desired Page On SC List: move to front of Active list, mark RW
 - Not on SC list: page in to front of Active list, mark RW; page out LRU victim at end of SC list

10/16/17

CS162 @UCB Fall 2017

Lec 15.19

Second-Chance List Algorithm (con't)

- How many pages for second chance list?
 - If 0 \Rightarrow FIFO
 - If all \Rightarrow LRU, but page fault on every page reference
- Pick intermediate value. Result is:
 - Pro: Few disk accesses (page only goes to disk if unused for a long time)
 - Con: Increased overhead trapping to OS (software / hardware tradeoff)
- With page translation, we can adapt to any kind of access the program makes
 - Later, we will show how to use page translation / protection to share memory between threads on widely separated machines
- Question: why didn't VAX include “use” bit?
 - Strecker (architect) asked OS people, they said they didn't need it, so didn't implement it
 - He later got blamed, but VAX did OK anyway

10/16/17

CS162 @UCB Fall 2017

Lec 15.20

Free List

- Keep set of free pages ready for use in demand paging
 - Freelist filled in background by Clock algorithm or other technique (“Pageout demon”)
 - Dirty pages start copying back to disk when enter list
- Like VAX second-chance list
 - If page needed before reused, just return to active set
- Advantage: faster for page fault
 - Can always use page (or pages) immediately on fault

10/16/17 CSI62 @UCB Fall 2017 Lec 15.21

Administrivia

- Midterm 2 coming up on **Mon 10/23 6:30-8:00PM**
 - All topics up to and including Lecture 16
 - » Focus will be on Lectures 10 – 16 and associated readings
 - » Projects 1 and 2
 - » Homework 0 – 2
 - Closed book
 - 2 pages hand-written notes both sides
 - Room assignment
 - » Li Ka Shing, GPB 100, Kreober 160
- Out on Wednesday (10/19) in Washington, DC
 - No office hour
 - Neeraja will start/teach the lecture

10/16/17 CSI62 @UCB Fall 2017 Lec 15.22

BREAK

10/16/17 CSI62 @UCB Fall 2017 Lec 15.23

Demand Paging (more details)

- Does software-loaded TLB need use bit?

Two Options:

 - Hardware sets use bit in TLB; when TLB entry is replaced, software copies use bit back to page table
 - Software manages TLB entries as FIFO list; everything not in TLB is Second-Chance list, managed as strict LRU
- Core Map
 - Page tables map virtual page → physical page
 - Do we need a reverse mapping (i.e. physical page → virtual page)?
 - » Yes. Clock algorithm runs through page frames. If sharing, then multiple virtual-pages per physical page
 - » Can't push page out to disk without invalidating all PTEs

10/16/17 CSI62 @UCB Fall 2017 Lec 15.24

Allocation of Page Frames (Memory Pages)

- How do we allocate memory among different processes?
 - Does every process get the same fraction of memory? Different fractions?
 - Should we completely swap some processes out of memory?
- Each process needs *minimum* number of pages
 - Want to make sure that all processes **that are loaded into memory** can make forward progress
 - Example: IBM 370 – 6 pages to handle SS MOVE instruction:
 - » instruction is 6 bytes, might span 2 pages
 - » 2 pages to handle *from*
 - » 2 pages to handle *to*
- Possible Replacement Scopes:
 - **Global replacement** – process selects replacement frame from set of all frames; one process can take a frame from another
 - **Local replacement** – each process selects from only its own set of allocated frames

10/16/17

CSI62 @UCB Fall 2017

Lec 15.25

Fixed/Priority Allocation

- **Equal allocation** (Fixed Scheme):
 - Every process gets same amount of memory
 - Example: 100 frames, 5 processes → process gets 20 frames
- **Proportional allocation** (Fixed Scheme)
 - Allocate according to the size of process
 - Computation proceeds as follows:
 - s_i = size of process p_i and $S = \sum s_i$
 - m = total number of frames
 - $$a_i = \text{allocation for } p_i = \frac{s_i}{S} \times m$$
- **Priority Allocation:**
 - Proportional scheme using priorities rather than size
 - » Same type of computation as previous scheme
 - Possible behavior: If process p_i generates a page fault, select for replacement a frame from a process with lower priority number
- Perhaps we should use an adaptive scheme instead???
- What if some application just needs more memory?


10/16/17

CSI62 @UCB Fall 2017

Lec 15.26

Page-Fault Frequency Allocation

- Can we reduce Capacity misses by dynamically changing the number of pages/application?




- Establish “acceptable” page-fault rate
 - If actual rate too low, process loses frame
 - If actual rate too high, process gains frame
- Question: What if we just don't have enough memory?

10/16/17

CSI62 @UCB Fall 2017

Lec 15.27

Thrashing



- If a process does not have “enough” pages, the page-fault rate is very high. This leads to:
 - low CPU utilization
 - operating system spends most of its time swapping to disk
- **Thrashing** ≡ a process is busy swapping pages in and out
- Questions:
 - How do we detect Thrashing?
 - What is best response to Thrashing?


10/16/17

CSI62 @UCB Fall 2017

Lec 15.28

Locality In A Memory-Reference Pattern

- Program Memory Access Patterns have temporal and spatial locality
 - Group of Pages accessed along a given time slice called the “Working Set”
 - Working Set defines minimum number of pages needed for process to behave well
- Not enough memory for Working Set \Rightarrow Thrashing
 - Better to swap out process?




10/16/17

CS162 @UCB Fall 2017

Lec 15.29

Working-Set Model



- Δ \equiv working-set window \equiv fixed number of page references
 - Example: 10,000 instructions
- WS_i (working set of Process P_i) = total set of pages referenced in the most recent Δ (varies in time)
 - if Δ too small will not encompass entire locality
 - if Δ too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program
- $D = \sum |WS_i| \equiv$ total demand frames
- if $D > m \Rightarrow$ Thrashing
 - Policy: if $D > m$, then suspend/swap out processes
 - This can improve overall system behavior by a lot!

10/16/17

CS162 @UCB Fall 2017

Lec 15.30

What about Compulsory Misses?

- Recall that compulsory misses are misses that occur the first time that a page is seen
 - Pages that are touched for the first time
 - Pages that are touched after process is swapped out/swapped back in
- **Clustering:**
 - On a page-fault, bring in multiple pages “around” the faulting page
 - Since efficiency of disk reads increases with sequential reads, makes sense to read several sequential pages
- **Working Set Tracking:**
 - Use algorithm to try to track working set of application
 - When swapping process back in, swap in working set

10/16/17

CS162 @UCB Fall 2017

Lec 15.31

Reverse Page Mapping (Sometimes called “Coremap”)

- Physical page frames often shared by many different address spaces/page tables
 - All children forked from given process
 - Shared memory pages between processes
- Whatever reverse mapping mechanism that is in place must be very fast
 - Must hunt down all page tables pointing at given page frame when freeing a page
 - Must hunt down all PTEs when seeing if pages “active”
- Implementation options:
 - For every page descriptor, keep linked list of page table entries that point to it
 - » Management nightmare – expensive
 - Linux 2.6: Object-based reverse mapping
 - » Link together memory region descriptors instead (much coarser granularity)

10/16/17

CS162 @UCB Fall 2017

Lec 15.32

Linux Memory Details?


- Memory management in Linux considerably more complex than the previous indications
- Memory Zones: physical memory categories
 - ZONE_DMA: < 16MB memory, DMAable on ISA bus
 - ZONE_NORMAL: 16MB → 896MB (mapped at 0xC0000000)
 - ZONE_HIGHMEM: Everything else (> 896MB)
- Each zone has 1 freelist, 2 LRU lists (Active/Inactive)
- Many different types of allocation
 - SLAB allocators, per-page allocators, mapped/unmapped
- Many different types of allocated memory:
 - Anonymous memory (not backed by a file, heap/stack)
 - Mapped memory (backed by a file)
- Allocation priorities
 - Is blocking allowed/etc

10/16/17

CSI62 ©UCB Fall 2017

Lec 15.33

Recall: Linux Virtual memory map



10/16/17

CSI62 ©UCB Fall 2017

Lec 15.34

Summary

- Replacement policies
 - FIFO: Place pages on queue, replace page at end
 - MIN: Replace page that will be used farthest in future
 - LRU: Replace page used farthest in past
- Clock Algorithm: Approximation to LRU
 - Arrange all pages in circular list
 - Sweep through them, marking as not "in use"
 - If page not "in use" for one pass, then can replace
- Nth-chance clock algorithm: Another approximate LRU
 - Give pages multiple passes of clock hand before replacing
- Second-Chance List algorithm: Yet another approximate LRU
 - Divide pages into two groups, one of which is truly LRU and managed on page faults.
- Working Set:
 - Set of pages touched by a process recently
- Thrashing: a process is busy swapping pages in and out
 - Process will thrash if working set doesn't fit in memory
 - Need to swap out a process

10/16/17

CSI62 ©UCB Fall 2017

Lec 15.35

Virtual Map (Details)

- Kernel memory not generally visible to user
 - Exception: special VDSO (virtual dynamically linked shared objects) facility that maps kernel code into user space to aid in system calls (and to provide certain actual system calls such as `gettimeofday()`)
- Every physical page described by a "page" structure
 - Collected together in lower physical memory
 - Can be accessed in kernel virtual space
 - Linked together in various "LRU" lists
- For 32-bit virtual memory architectures:
 - When physical memory < 896MB
 - » All physical memory mapped at 0xC0000000
 - When physical memory ≥ 896MB
 - » Not all physical memory mapped in kernel space all the time
 - » Can be temporarily mapped with addresses > 0xCC000000
- For 64-bit virtual memory architectures:
 - All physical memory mapped above 0xFFFF800000000000

10/16/17

CSI62 ©UCB Fall 2017

Lec 15.36