Lecture #26: Introduction to R	luntime Organization	Status	
		 Lexical analysis 	
		- Produces tokens	
		- Detects & eliminates illegal tokens	
		• Parsing	
		- Produces trees	
		– Detects & eliminates ill-formed par	se trees
		 Static semantic analysis 	
		 Produces decorated tree with addit Detects & eliminates remaining stat 	ional information attached tic errors
		 Next are the dynamic "back-end" phas 	es: ⇐ we are here
		– Code generation (at various semanti – Optimization	ic levels)
Last modified: Mon Mar 30 00:57:34 2015	CS164: Lecture #26 1	Last modified: Mon Mar 30 00:57:34 2015	C5164: Lecture #26 2
Run-time environ	ments	Code Generation Goals and	d Considerations
Before discussing code generation, we need trying to generate.	d to understand what we are	 Correctness: execution of generated the programs' specified dynamic seman 	code must be consistent with ntics.
• We'll use the term virtual machine to re	fer to the compiler's target.	• In general, however, these semantics of	do not completely specify be-
• Can be just a bare hardware architectur	e (small embedded systems).	havior, often to allow compiler to acco	mplish other goals, such as
 Can be an interpreter, as for Java, or a ditional compilation at execution, as in r 	in interpreter that does ad- nodern Java JITs	 Speed: produce code that executes as meets certain timing constraints (as in 	quickly as possible, or reliably a real-time systems).
• Can even be a "machine" whose machine ming language such as C. Java, or Javas	anguage is another program- cript	 Size: minimize size of generated programmed programme	ram or of runtime data struc-
• For now we'll stick to hardware + conve	entions for using it (the APT.	 Speed and size optimization can be cor 	nflicting goals. Why?
application programmer's interface) + so	ome runtime-support library.	• Compilation speed: especially during de	velopment or when using JITs.

• Most complications in code generation come from trying to be fast as well as correct, because this requires attention to special cases.

Subgoals and Constraint	ts	Activations and Lifetimes	(Extents)	
• Subgoals for improving speed and size:		• An invocation of procedure <i>P</i> is an <i>activation</i>	on of P.	
– Minimize instruction counts. – Keep data structure static, known at compil	ation (e.g., known con-	• The <i>lifetime of an activation</i> of <i>P</i> is all the steps to execute <i>P</i> , including all the steps in procedures <i>P</i> calls.		
 stant offsets to fields). Contrast Java and Python. Maximize use of registers ("top of the memory hierarchy"). Subgoals for improving compilation speed: Try to keep analyses as <i>local</i> as possible (single statement, block, procedure), because their compilation-time cost tends to be non-linear. Simplify assumptions about control flow: procedure calls "always" return statements generally execute in sequence. (Where are 		 The <i>lifetime (extent) of a variable</i> is the portion of execution during which that variable exists (whether or not the code currently executing can reference it). Lifetime is a dynamic (run-time) concept, as opposed to scope, which is static. 		
		these violated?)		 Other variables have extents that are not dure calls and returns.
Last modified: Mon Mar 30 00:57:34 2015	C5164: Lecture #26 5	Last modified: Mon Mar 30 00:57:34 2015	CS164: Lecture #26 6	
Memory Layout		Activation Records	s	
Memory Layout Characteristics of procedure activations and var following typical data layout for a (single-threade	iables give rise to the ed) program:	• The information needed to manage one proc an activation record (AR) or (stack) frame.	s edure activation is called	
Memory Layout Characteristics of procedure activations and vari following typical data layout for a (single-threade Execution stack	iables give rise to the ed) program: — Highest memory address	 Activation Records The information needed to manage one proceed an activation record (AR) or (stack) frame. If procedure F (the caller) calls G (the caller) record contains a mix of data about F 	s edure activation is called	
Memory Layout Characteristics of procedure activations and vari following typical data layout for a (single-threade Execution stack ("stack segment")	iables give rise to the ed) program: — Highest memory address	 Activation Records The information needed to manage one proce an activation record (AR) or (stack) frame. If procedure F (the caller) calls G (the caller) calls G (the caller) record contains a mix of data about F Return address to instructions in F. 	s edure activation is called	
Memory Layout Characteristics of procedure activations and vari following typical data layout for a (single-threade Execution stack ("stack segment")	iables give rise to the ed) program: — Highest memory address	 Activation Records The information needed to manage one procean activation record (AR) or (stack) frame. If procedure F (the caller) calls G (the caltion record contains a mix of data about F Return address to instructions in F. Dynamic link to the AR for F. 	s redure activation is called	
Memory Layout Characteristics of procedure activations and vari following typical data layout for a (single-threade Execution stack ("stack segment")	iables give rise to the ed) program: — Highest memory address	 Activation Records The information needed to manage one proce an activation record (AR) or (stack) frame. If procedure F (the caller) calls G (the cal tion record contains a mix of data about F Return address to instructions in F. Dynamic link to the AR for F. Space to save registers needed by F. 	s edure activation is called	
Memory Layout Characteristics of procedure activations and vari following typical data layout for a (single-threade Execution stack ("stack segment")	iables give rise to the ed) program: — Highest memory address	 Activation Records The information needed to manage one proce an activation record (AR) or (stack) frame. If procedure F (the caller) calls G (the cal tion record contains a mix of data about F Return address to instructions in F. Dynamic link to the AR for F. Space to save registers needed by F. Space for G's local variables. 	s edure activation is called allee, typically G's activa- and G:	
Memory Layout Characteristics of procedure activations and vari following typical data layout for a (single-threade Execution stack ("stack segment")	iables give rise to the ed) program: — Highest memory address	 Activation Records The information needed to manage one proce an activation record (AR) or (stack) frame. If procedure F (the caller) calls G (the cal tion record contains a mix of data about F Return address to instructions in F. Dynamic link to the AR for F. Space to save registers needed by F. Space for G's local variables. Information needed to find non-local variables 	s edure activation is called ullee, typically G's activa- and G: riables needed by G.	
Memory Layout Characteristics of procedure activations and vari following typical data layout for a (single-threaded Execution stack ("stack segment") Dynamic data ("heap")	iables give rise to the ed) program: — Highest memory address	 Activation Records The information needed to manage one proce an activation record (AR) or (stack) frame. If procedure F (the caller) calls G (the caller) calls G (the caller) calls G (the caller) calls C (the caller) calles C (t	s edure activation is called allee, typically G's activa- and G: riables needed by G. Its, arguments to and re-	
Memory Layout Characteristics of procedure activations and vari following typical data layout for a (single-threade Execution stack ("stack segment") Dynamic data ("heap") Static data ("data segment(s)")	iables give rise to the ed) program: — Highest memory address	 Activation Records The information needed to manage one proce an activation record (AR) or (stack) frame. If procedure F (the caller) calls G (the calion record contains a mix of data about F Return address to instructions in F. Dynamic link to the AR for F. Space to save registers needed by F. Space for G's local variables. Information needed to find non-local var Temporary space for intermediate result turn values from functions that G calls. Assorted machine status needed to rest masks, floating-point unit parameters). 	s edure activation is called allee, typically G's activa- and G: riables needed by G. Its, arguments to and re- store F's context (signal	
Memory Layout Characteristics of procedure activations and vari following typical data layout for a (single-threade Execution stack ("stack segment") Dynamic data ("heap") Static data ("data segment(s)") Instructions ("text segment(s)")	iables give rise to the ed) program: — Highest memory address	 Activation Records The information needed to manage one proce an activation record (AR) or (stack) frame. If procedure F (the caller) calls G (the calion record contains a mix of data about F Return address to instructions in F. Dynamic link to the AR for F. Space to save registers needed by F. Space for G's local variables. Information needed to find non-local var Temporary space for intermediate resulturn values from functions that G calls. Assorted machine status needed to resemasks, floating-point unit parameters). Depending on architecture and compiler, regord AR (at times), especially parameters, repointers to the current stack top and frame 	s edure activation is called allee, typically G's activa- and G: riables needed by G. Its, arguments to and re- store F's context (signal gisters typically hold part return values, locals, and le.	

Calling Conventions		Static Store	age
 Many variations are possible: Can rearrange order of frame elements. Can divide caller/callee responsibilities d Don't need to use an array-like implement use a linked list of ARs. An organization is better if it improves exect code generation The compiler must determine, at compile-tint tion records and generate code that correct the activation record. Furthermore, it is common to compile prowithout access of each other's details, which position of <i>calling conventions</i>. 	ifferently. tation of the stack: can ution speed or simplifies ne, the layout of activa- tly accesses locations in cedures separately and h motivates the the im-	 Here, "static storage" refers to variables whose extent is an entire execution and whose size is typically fixed before execution. Not generally stored in an activation record, but assigned a fixe address once. In C/C++ variables with file scope (declared static in C) and wite external linkage ("global") are in static storage. Java's "static" variables are an odd case: they don't really fit this picture (why?) 	
Last modified: Mon Mar 30 00:57:34 2015 Heap Storage	C5164: Lecture #26 9	Last modified: Mon Mar 30 00:57:34 2015 Achieving Runtime Fffe	C5164: Lecture #26 10
• Variables whose extent is greater than that	of the AR in which they	• Language design and runtime design	interact. Semantics of func-
are created can't be kept there:		tions make good example.	
<pre>Bar foo() { return new Bar(); }</pre>		 Levels of function features: 	
 Typically allocated out of an area called th the same as the heap used for priority qeue 	e heap (confusingly, not s!)	 1. Hum: no recursion, no nesting, fixed by compiler. 2. Add recursion. 3. Add variable-sized unboxed data. 4. Allow nesting of functions, up-level 5. Allow function values w/ properly n 6. Allow general closures. 7. Allow continuations. Tension between these effects and st Machine languages typically only maddresses like R + C, where R is a relatively small integer constant Therefore, fixed offsets good, data 	addressing. lested accesses only. tructure of machines: ake it easy to access things at an address in a register and <i>C</i> nt. ta-dependent offsets bad.
L	651/4-1 #67		651(4)

1: No recursion, no nesting, fixed-sized data

- Total amount of data is bounded, and there is only one instantiation of a function at a time.
- So all variables, return addresses, and return values can go in fixed locations.
- No stack needed at all.
- Characterized FORTRAN programs in the early days.
- In fact, can dispense with call instructions altogether: expand function calls in-line. E.g.,
 - def f (x): x *= 42 y = 9 + x; g (x, y) $\implies becomes \implies x_1 = 3$ $x_1 = 3$ $y_1 = 9 + x_1$ $g (x_1, y_1)$

f (3)

• However, program may get bigger than you want. Typically, one inlines only small, frequently executed functions.

Last modified: Mon Mar 30 00:57:34 2015

CS164: Lecture #26 13

2: Add recursion

- Now, total amount of data is unbounded, and several instantiations of a function can be active simultaneously.
- Calls for some kind of expandable data structure: a stack.
- However, variable sizes still fixed, so size of each activation record (stack frame) is fixed.
- All local-variable addresses and the value of dynamic link are known offsets from stack pointer, which is typically in a register.
- (The diagram shows the conventions we use in the ia32, where we'll define a stack frame as starting *after* the return address.)



1: Calling conventions

- If we don't use function inlining, will need to save return address, parameters.
- There are many options. Here's one example, from the IBM 360, of calling function F from G and passing values 3 and 4:

	-			
	GArgs	DS	2F	Reserve 2 4-byte words of static storage */
		ENTRY	G	
(G			
		LA	R1,GArgs	Load Address of arguments into register 1
		LA	R0,3	Store 3 and 4 in GArgs+0 and GArgs+4
		ST	R0,GArgs	
		LA	R0,4	
		ST	R0,GArgs+4	
		BAL	R14,F	Call ("Branch and Link") to F, R14 gets return point
and	d F m	ight	contain	
I	FRet	DS	F	
		ENTRY	F	
]	F	ST	R14,FRet	Save return address
		L	R2,0(R1)	Load first argument.
		L	R14,FRet	Get return address
		BR	R14	Branch to it

Last modified: Mon Mar 30 00:57:34 2015

CS164: Lecture #26 14

2: Calling Sequence when Frame Size is Fixed

- So dynamic links not really needed.
- Suppose f calls g calls f, as at right.
- When called, the initial code of g (its prologue) decrements the stack pointer by the size of g's activation record.
- g's exit code (its epilogue):
 - increments the stack pointer by this same size,
 - pops off the return address, and
 - branches to address just popped.



2: Calling sequence from ia32

Assembly excerpt (GNU operand order):

	/ PRO = Prologue, EPI	= Epilogue
C code:	f: / Return add subl \$4, %esp movl \$1, (%esp)	ress (RA) at SP, x at SP+4, y at SP+8 / PRO: Decrement SP to make space for s / s = 1
<pre>f (int x, int y) { int s; s = 1; while (y > 0) { s *= x; y -= 1; } return s;</pre>	<pre>cmpl \$0, 12(%esp) jle .L3 movl (%esp), %eax imull 8(%esp), %eax movl %eax, (%esp) leal 12(%esp), %eax decl (%eax) jmp .L2 L2.</pre>	<pre>/ compare 0 with y (now at SP+12) / tmp = s / tmp *= x / s = tmp / tmp = &y / *tmp -= 1</pre>
<pre>} int g(int q) { return f(q, 5); }</pre>	<pre>movl (%esp), %eax addl \$4, %esp ret g: movl \$5, 4(%esp) movl 12(%esp), %eax movl %eax, (%esp) call f next:</pre>	<pre>/ return s in EAX / EPI: Restore stack pointer so RA on top, / EPI: then pop RA and return. / Put q and 5 on stack (q on top). / tmp = q / top of stack = q / branch to f and push address of next.</pre>
Last modified: Mon Mar 30 00:57:34 2015		CS164: Lecture #26 17

Other Uses of the Dynamic Link

- Often use dynamic link even when size of AR is fixed.
- Allows use of same strategy for all ARs, simplifies code generation.
- Makes it easier to write general functions that *unwind* the stack (i.e., pop ARs off, thus returning).

3: Add Variable-Sized Unboxed Data

- "Unboxed" means "not on heap."
- Boxing allows all quantities on stack to have fixed size.
- So Java implementations have fixedsize stack frames.
- But does cost heap allocation, so some languages also provide for placing variable-sized data directly on stack ("heap allocation on the stack")
- alloca in C, e.g.
- Now we do need dynamic link (DL).
- But can still insure fixed offsets of data from frame base (*frame pointer*) using pointers.
- To right, f calls g, which has variablesized unboaxed array (see right).



Last modified: Mon Mar 30 00:57:34 2015

CS164: Lecture #26 18

3: Calling sequence for the ia32

Assembly excerpt (GNU operand order):

	f: / Return add	lress (RA) at SP, x at SP+4, y at SP+8
	pushl %ebp	/ PRO: Save old dynamic link.
C code:	movl %esp, %ebp	/ PRO: Set ebp to current frame base.
<pre>int f (int x, int y)</pre>	subl \$4, %esp movl \$1, -4(%ebp) L2:	<pre>/ PRO: Decrement SP to make space for s / s = 1</pre>
{ int s; s = 1:	cmpl \$0, 12(%ebp) jle .L3	/ compare 0 with y (now at BP+12)
while $(v > 0)$ {	movl -4(%ebp), %eax	x / tmp = s
s *= x;	imull 8(%ebp), %eax	/ tmp *= x
v -= 1;	movl %eax, -4(%ebp)	/ s = tmp
}	leal 12(%ebp), %eax	t / tmp = &y
<pre>return s; }</pre>	decl (%eax) jmp .L2 .L3:	/ *tmp -= 1
	movl -4(%ebp), %eax	/ return s
r(int a)	leave	/ EPI: Restore %esp to %ebp+4 and %ebp to 0(%ebp
s a current de la current de l	ret	/ EPI: then pop RA and return.
<pre>return f(q, 5); }</pre>	<pre>g: movl \$5, 4(%esp) movl 8(%ebp), %eax movl %eax, (%esp) call f next:</pre>	<pre>/ Put q and 5 on stack (q on top). / tmp = q / top of stack = q / branch to f and push address of next.</pre>

4: Allow Nesting of Functions, Up-Level Addressing

q's

frame

:

q's

frame

q's

frame

f's

frame

- When functions can be nested, there are three classes of variable:
 - a. Local to function.
- b. Local to enclosing function.
- c. Global
- Accessing (a) or (c) is easy. It's (b) that's interesting.
- Consider (in Python):
 - def f (): y = 42 # Local to f def g (n, q): if n == 0: return q+y else: return g (n-1, q*2)
- Here, y can be any distance away from top of stack.

Last modified: Mon Mar 30 00:57:34 2015

CS164: Lecture #26 21

Top of stack

Enclosing f

How far???

Calling sequence for the ia32: f0

Assembly excerpt for f0:

C code:	f0:	/ Does not	need to be passe	ed a s	static link
<pre>int f0 (int n0) { int s = -n0; int g1 () { return s; } int f1 (int n1) { int f2 () { return n0 + n1</pre>)) / St /	<pre>/ Joes hot push1 mov1 sub1 mov1 mov1 mov1 mov1 mov1 lea1 mov1 cal1 leave ret atic link in int </pre>	heed to be passe %ebp %esp, %ebp \$40, %esp 8(%ebp), %eax %eax, -16(%ebp) -16(%ebp), %eax %eax, -12(%ebp) -16(%ebp), %eax \$10, (%esp) %eax, %ecx f1 hto f0's frame po n0' s	ed a's / / / / / / / / / / / points	PRO PRO PRO Fetch nO Move nO to new local variable Negate nO and store in s Compute static link to fO's frame Pass argument 10 and static link to f1 EPI EPI to: Copy of nO

Static Links

- To overcome this problem, go back to environment diagrams!
- Each diagram had a pointer to lexically enclosing environment
- In Python example from last slide, each 'g' frame contains a pointer to the 'f' frame where that 'g' was defined: the *static link* (SL)
- To access local variable, use frame-base pointer (or maybe stack pointer).
- To access global, use absolute address.
- To access local of nesting function, follow static link once per difference in levels of nesting.



Last modified: Mon Mar 30 00:57:34 2015

CS164: Lecture #26 22

Calling sequence for the ia32: f1

f1: /	Static 1:	ink to f0's frame is	; in %ecx
	pushl	%ebp	/ PRO
	movl	%esp, %ebp	/ PRO
C code:	pushl	%esi	/ PRO: Save %esi
int	pushl	%ebx	/ PRO: Save %ebx
f(t)	subl	\$32, %esp	/ PRO
s (int no)	movl	%ecx, %ebx	/ Save link to f0's frame
i = -n0	movl	8(%ebp), %eax	/ Move n1
$\operatorname{IIIC} S = -\operatorname{IIO},$	movl	%eax, -16(%ebp)	/to new local
int gi () $(1 \text{ feturil } S, f$	movl	%ebx, -12(%ebp)	/ Save static link to f0 in local
$\operatorname{III}_{\operatorname{int}} \operatorname{III}_{\operatorname{III}} \operatorname{III}_{\operatorname{III}}$	movl	4(%ebx), %edx	/ Fetch s from f0's frame
$\frac{111112}{12} = 10 + 11$	movl	%edx, (%esp)	/ And pass to f2
	leal	-16(%ebp), %ecx	/ Pass static link to my frame to f2
+ S + gi (),	call	f2	
f_{1}	movl	%eax, %esi	/ Save f2(s)
$+ \sigma_1 ()$	movl	(%ebx), %eax	/ Fetch n0 from f0's frame
' gi (),	movl	%eax, (%esp)	/ and pass to f1
$\int f_1 (10)$	movl	%ebx, %ecx	/ Also pass on my static link
11 (10),	call	f1	
ſ	addl	%eax, %esi	/ Compute $f2(s) + f1(n0)$
/* Static link to f1 points to:	movl	%ebx, %ecx	/ Pass same static link to g1
int n1? Conv of n1	call	g1	
int SI Static link	leal	(%esi,%eax), %eax	/ Compute f2(s)+f1(n0)+g1()
to f0's frame */	addl	\$32, %esp	/ EPI
oo io b iidme .,	popl	%ebx	/ EPI: restore %ebx
	popl	%esi	/ EPI: restored %esi
	popl	%ebp	/ EPI
	ret		/ EPI
modified: Mon Mar 30 00:57:34 2015			CS164: Lecture #26 24

Calling sequence for the ia32: g1

C code:

int f2: / Static link (into f1's frame) in %ecx C code: f0 (int n0) pushl %ebp / PRO { / PRO movl %esp, %ebp Assembly excerpt for g1: int int s = -n0;f0 (int n0) pushl %ebx / PRO: Save %ebx / Fetch static link to f0 int g1 () { return s; } g1: / Static link (to f0's frame) in %ecx ſ movl %ecx. %eax int f1 (int n1) { / PRO int s = -n0;pushl %ebp int f2 () { movl %esp, %ebp / PRO int g1 () { r movl return n0 + n1 %ecx. %eax / Fetch s from ... int f1 (int n + s + g1 (); 4(%eax), %eax / ... f0's frame int f2 () { movl / EPI } popl %ebp return n0 return f2 (s) + f1 (n0) / EPI ret + g1 (); } } return f2 (f1 (10); + g1 } } f1 (10); } CS164: Lecture #26 25 Last modified: Mon Mar 30 00:57:34 2015 Last modified: Mon Mar 30 00:57:34 2015 The Global Display Using the global display (sketch) Historically, first solution to nested function q1's Сс problem used an array indexed by call level,

- rather than static links. def f0 (): q = 42; g1 ()def f1 (): def f2 (): ... g2 () ... def g2 (): ... g2 () ... g1 () f2 () ... f1 () ...
 - def g1 (): ... f1 () ...
- Each time we enter a function at lexical level k(i.e., nested inside k functions), save pointer to its frame base in DISPLAY[k]; restore on exit.
- Access variable at lexical level k through DISPLAY[k].
- Relies heavily on scope rules and proper function-call nesting
- frame q2's frame g2's frame f2's frame g2 2 g1 1 f0 0 f1's frame f1's frame g1's frame f0's DISPLAY frame

CS164: Lecture #26 27

	movl	4(%eax), %edx	/ from f1's frame
eturn s; }	movl	(%edx), %ecx	/ to get n0 from f0's frame
1) {	movl	(%eax), %edx	/ Fetch n1 from f1's frame
	addl	%edx, %ecx	/ Add n0 + n1
) + n1	movl	4(%eax), %edx	/ Fetch static link to f0 again
s + g1 ();	movl	4(%edx), %edx	/ Fetch s from f0's frame
	leal	(%ecx,%edx), %ebx	/ And add to n0 + n1
(s) + f1 (n0)	movl	4(%eax), %eax	/ Fetch static link to f0
. ();	movl	%eax, %ecx	/ and pass to g1
	call	g1	
	leal	(%ebx,%eax), %eax	/ Add g1() to n0 + n1 + s
	popl	%ebx	/ EPI: Restore %ebx
	popl	%ebp	/ EPI
	ret		/ EPI

Calling sequence for the ia32: f2

Assembly excerpt for f2:

CS164: Lecture #26 26

C code:	
0.0000	f0:
int	<pre>movl _DISPLAY+0,%eax / PRO: Save old _DISPLAY[0]</pre>
f0 (int n0)	movl %eax,-12(%ebp) / PRO:somewhere
{	<pre>movl %epb,_DISPLAY+0 / PRO: Put my %ebp in _DISPLAY[0]</pre>
int $s = -n0;$	
int g1 () { return s; }	movl -12(%ebp),%ecx / EPI: Restore old _DISPLAY[0]
int f1 (int n1) {	movl %ecx,_DISPLAY+0 / EPI
int f2 () {	
return n0 + n1	f1:
+ s + g1 ();	<pre>movl _DISPLAY+4,%eax / PRO: Save old _DISPLAY[1]</pre>
}	movl %eax,-12(%ebp) / PRO: somewhere
return f2 (s) + f1 (n0)	<pre>movl %ebp,_DISPLAY+4 / PRO: Put my %ebp in _DISPLAY[1]</pre>
+ g1 ();	likewise for epilogue.
}	
f1 (10);	f2 and g1: no extra code, since they have no nested functions.
1	

}

5: Allow Function Values, Properly Nested Access

- In C, C++, no function nesting.
- So all non-local variables are global, and have fixed addresses.
- Thus, to represent a variable whose value is a function, need only to store the address of the function's code.
- But when nested functions possible, function value must contain more.
- When function is finally called, must be told what its static link is.
- Assume first that access is properly nested: variables accessed only during lifetime of their frame.
- So can represent function with address of code + the address of the frame that contains that function's definition.
- It's environment diagrams again!!

Function Value Representation



- Call f0 from the main program; look at the stack when f2 finally is called (see right).
- When f2's value (as a function) is computed, current frame is that of f1. That is stored in the value passed to h1.
- Easy with static links; global display technique does not fare as well [why?]



CS164: Lecture #26 29 CS164: Lecture #26 30 Last modified: Mon Mar 30 00:57:34 2015 Last modified: Mon Mar 30 00:57:34 2015 6: General Closures **Representing Closures** Value of incr(2) • Could just forbid this case (as • What happens when the frame some languages do): that a function value points to goes away? - Algol 68 would not allow delta, • If we used the previous reprepointer to f (last slide) to be & n returned from incr. sentation (#5), we'd get a dan-SL gling pointer in this case: - Or, one could allow it, and do code for f incr's temp something random when f (i.e. def incr (n): frame storage via delta) is called. delta = nwith etc. def f (x): • Scheme and Python allow it and delta DL return delta + x do the right thing. SL Value of incr(2)ra return f DL • But must in general put local : ra variables (and a static link) in a

p2 = incr(2)print p2(3)



record on the heap, instead of on the stack.



Representing Closures

- Could just forbid this case (as some languages do):
 - Algol 68 would not allow pointer to f (last slide) to be returned from incr.
 - Or, one could allow it, and do something random when f (i.e. via delta) is called.
- Scheme and Python allow it and do the right thing.
- But must in general put local variables (and a static link) in a record on the heap, instead of on the stack.
- Now frame can disappear harmlessly.

•	
:	

CO

7: Continuations

• Suppose function return were not the end?

<pre>def f (cont): return cont x = 1 def g (n): global x, c if n == 0: print "a", x, n, c = call_with_continuation (f) print "b", x, n, else: g(n-1); print "c", x, n, g(2); x += 1; print; c() • The continuation, c, passed to f is "the r is supposed to happen after I return from c an be used to implement eventions. the con be used to implement eventions. the con be used to implement eventions. the con be used to implement eventions.</pre>	<pre># Prints: # a 1 0 b 1 0 c 1 1 c 1 2 # b 2 0 c 2 1 c 2 2 # b 3 0 c 3 1 c 3 2 function that does whatever om f."</pre>	 Plain: no recursion, no nest- ing, fixed-sized data with size known by compiler, first-class function values. #1 + recursion #2 + Add variable-sized un- boxed data #3 - first-class function values + Nested functions, up-level ad- dressing #4 + Function values w/ prop- erly nested accesses: functions #4 + Function values w/ prop- erly nested accesses: functions #4 + Function values w/ prop- erly nested accesses: functions 	ie in .k y. n-
 Can be used to implement exceptions, the 	nreads, co-routines.	passed as parameters only. doesn't work so well)	
• Implementation? Nothing much for it bu on the heap.	it to put all activation frames	6. #5 + General closures: first- Store local variables and staticlass functions returned from link on heap. functions or stored in variables	ic
 Distributed cost. 		7. #6 + Continuations Put everything on the heap.	
• However, we can do better on special co	ases like exceptions.		
Last modified: Mon Mar 30 00:57:34 2015	CS164: Lecture #26 33	Last modified: Mon Mar 30 00:57:34 2015 CS164: Lecture #	26 34

Summary

Solution

Problem